

Listermann Brewery Supply

DoppelBock

Instruction Sheet

Original Gravity: 1.072 24 IBUs

Ingredients Included:

10 lbs. of Canadian light syrup
2 lb. Bonlander malt
0.125 lbs. Chocolate malt
1.5 oz. Hallertau hop pellets
5 oz (3/4 cup) priming sugar
1 packet of Saflager lager yeast
1 large grain bag
1 small hop bag
55 crown caps

Supplies Needed:

Sanitizer powder

Equipment Required:

12 qt. or larger pot
thermometer - freezing to boiling
large stirring spoon
fermenter - six gallon minimum, with drilled lid
airlock with stopper

55 12oz. bottles

Procedure:

Pour the Bonlander malt (pale colored grain) into the grain bag and knot or tie the bag about half-way up. Pour the darker grain mixture into the bag and tie off sausage style. Pour about 2 gallons of water into the pot, add the grain bag and start to heat on a stove. When the temperature of the water reaches 150°F, reduce heat and allow to simmer for 30 minutes. Do not allow the temperature to rise above 160°F. Reduce with cold water if necessary. Occasionally lift the bag, allow it to drain, and return to the water. After simmering, remove the bag and allow to drain over the pot. Do not squeeze. Discard (or compost) the spent grains.

Increase temperature until boiling is reached and remove from the heat. Stir the extract syrup into the pot until dissolved. Pour the hop pellets into a bag, tie shut and add to the pot. Return the pot to heat and boil for 60 minutes. Watch for boil-overs - they will happen. Keep a glass of cold water close by to pour in if a boil over happens. The total boil time is 60 minutes.

Remove the hop bag and cool the pot of wort (unfermented beer) by immersing it in a sink or tub of cold water. The water will need to be changed periodically as it warms. Ice can be added to the sink toward the end of the cooling.

Make up a solution of Sanitizer by mixing a teaspoon of sanitizing powder with water in the jar. Sanitize the fermenter by pouring a couple of cups of solution and sloshing it around until all surfaces are wetted. Rinse the fermenter twice.

When the wort is cooled to about 100°F, pour it into the fermenter and fill with tap water to the five gallon level. The temperature should be between 65° and 75°F. Open the yeast package and pour it in. Violently stir (whip) the wort with a sanitized spoon to aerate.

Wipe the lid with Sanitizer and rinse. Fit the lid to the fermenter and fit the sanitized air lock, half filled with water to the lid's hole.

Place the fermenter in a place where the temperature will be between 65° and 75°F. In 12 to 24 hours the air lock should start to bubble and a thick foam will form on the surface of the wort. Over 5 to 7 days, the bubbles will slow to about one every other minute and the foam will start to disappear. (Note: It is not unusual for the fermentation to be complete very quickly, 1-2 days, especially if the