

Listermann Brewery Supply

Bavarian Dunkelweizen

Instruction Sheet

Original Gravity: 1.050

14 IBUs

Ingredients Included:

7 lbs. Wheat Malt Extract
0.5 lbs. Chocolate Wheat
0.5 lbs Caramunich Malt
0.5 lbs Dark Munich Malt
1 oz Hallertau Hop Pellets
1 Safbrew T-58 yeast
3 small bags
55 crown caps
5 oz (3/4 cup) priming sugar

Supplies Needed:

Sanitizer powder

Equipment Required:

12 qt. or larger pot
thermometer - freezing to boiling
a large stirring spoon
fermenter - six gallon minimum, with drilled lid
airlock with stopper
55 12oz. bottles

Procedure:

Divide the malt grist into a two bags and knot or tie shut. Pour about 2 gallons of water into the pot, add the grain bag and start to heat on a stove. When the temperature of the water reaches 150°F-160°F, reduce heat and allow to steep for 30 minutes. Do not allow the temperature to rise above 160°F. Occasionally lift the bag, allow it to drain and return to the water. After steeping, remove the bag and allow to drain over the pot. Do not squeeze.

Increase temperature until boiling is reached and remove from the heat. Stir the extract syrup into the pot until dissolved. Pour the hop pellets into a bag, tie shut and add to the pot. Return the pot to heat and boil for 60 minutes. Watch for boil over- they will happen. Keep a glass of cold water close by to pour in if a boil over happens.

Remove the hops and cool the pot of wort (unfermented beer) by immersing it in a sink or tub of cold water. The water will need to be changed periodically as it warms. Ice can be added to the sink toward the end of the cooling.

Make up a solution of Sanitizer by mixing a teaspoon of sanitizing powder with water in the jar. Sanitize the fermenter by pouring a couple of cups of solution and sloshing it around until all surfaces are wetted. Rinse the fermenter twice.

When the wort is cooled to about 100°F, pour it into the fermenter and fill with tap water to the five gallon level. The temperature should be between 65° and 75°F. Open the yeast vial and pour it in. Violently stir (whip) the wort with a sanitized spoon to aerate.

Wipe the lid with Sanitizer and rinse. Fit the lid to the fermenter and fit the sanitized air lock, half-filled with water to the lid's hole.

Place the fermenter in a place where the temperature will be between 65° and 75°F. In 12 to 24 hours the air lock should start to bubble and thick foam will form on the surface of the wort. Over 5 to 7 days, the bubbles will slow to about one every other minute and the foam will start to disappear. (Note: It is not unusual for the fermentation to be complete very quickly, 1-2 days, especially if the temperature is warm.) Always wait until the foam is gone before proceeding to bottling. There is no need to rush to bottling: the beer will be fine if left in the carboy for several weeks.